

# The **tabulary** package\*

David Carlisle

2008/12/01

## 1 User Documentation

```
\begin{tabulary}{<length>}{<pream>} ... \end{tabulary}
```

The rather daft name may change in a later release but it is a pun on `tabularx`, which itself was a pun on `tabular*`...

These environments work pretty much like the standard `tabular` environment (or more correctly, the enhanced version from the `array` package) except that there are more possibilities for the column types.

**LCRJ** These new ‘uppercase’ column types are only activated in the `tabulary` environment. In order to make the total table width equal to `<length>` the LCRJ columns are converted to p columns (with `\raggedright`, `\centering`, or `\raggedleft` or normal justification respectively applied). The width of these converted columns is proportional to the natural width of the longest entry in each column.

To stop very narrow columns being too ‘squeezed’ by this process any columns that are narrower than `\tymin` are set to their natural width. This length may be set with `\setlength` and is arbitrarily initialised to 10pt. (If you know that a column will be narrow, it may be preferable to use, say, `c` rather than `C` so that the `tabulary` mechanism is never invoked on that column.)

Similarly one very large entry can force its column to be too wide. So to prevent this, all columns with natural length greater than `\tymax` are set to the same width (with the proportion being taken as if the natural length was *equal* to `\tymax`). This is initially set to twice the text width..

Narrow p columns are sometimes quite hard to set, and so you may redefine the command `\tyformat` to be any declarations to make just after the `\centering` or `\ragged...` declaration. By default it redefines `\everypar` to insert a zero space at the start of every paragraph, so the first word may be hyphenated. (See DogBook).

As the environment makes a standard L<sup>A</sup>T<sub>E</sub>X box, it will be indented by the paragraph indent at the start of a paragraph, and so will not fit on a line if given argument `\textwidth` unless it is preceded by `\noindent` or is in a `center` environment or some other environment with zero paragraph indent.

---

\*This file has version number v0.9, last revised 2008/12/01.

## 2 Features

You can use `\multicolumn` but if the multicolumn text turns out to be longer than the final calculated widths of the columns that it spans, then the final table will be too wide.

`\verb` doesn't work. (except in restricted version as in `tabularx`)

The whole table is evaluated twice, so take care with some `TeX` constructions that may have side effects like writing to files.

## 3 Options

The following package option is defined:

**debugshow** Causes a lot of stuff to appear on the terminal. I find this invaluable, you may find it less so.

## 4 Examples

With C columns

|   |   |              |   |
|---|---|--------------|---|
| 1 | the rain in spain<br>falls mainly on the<br>plain | (an @ expr.) | the rain in spain falls mainly on the<br>plain the rain in spain falls mainly on<br>the plain |
| a | b   | (an @ expr.) | c   |
| a | b b   | (an @ expr.) | c c   |
| a |   |              |   |

With J columns

|   |   |              |   |
|---|---|--------------|---|
| 1 | the rain in spain<br>falls mainly on the<br>plain | (an @ expr.) | the rain in spain falls mainly on the<br>plain the rain in spain falls mainly on<br>the plain |
| a | b   | (an @ expr.) | c   |
| a | b b   | (an @ expr.) | c c   |
| a |   |              |   |

With L, R and C columns, and a \multicolumn

|   |   |   |   |
|---|---|---|---|
| 1 | the rain in spain<br>falls mainly on<br>the plain | the rain in spain falls mainly on<br>the plain the rain in spain falls<br>mainly on the plain | and now for<br>something<br>completely<br>different |
| x |   | some multicolumn text across columns 2–4  |   |
| a | b   | c   | d   |
| a | b b   | c c   | d d   |
| a |   |   |   |

The following examples attempt to show the effect of the `\tymmin` and `\tymax` parameters. One should also perhaps note that `\tymax` refers to the total column width (including any inter-column space, rules etc) but `\tymmin` just refers to the width of the column entry (like the argument to the standard `p` column).

```
\tymmin=0pt  
\tymax=\maxdimen
```

Note how the first column is ‘squeezed’. In fact it is in such a narrow column that even ‘a’ produces an overfull box warning!

```
\tymmin=20pt  
\tymax=\maxdimen
```

Here increase `\tymmin` so that columns b and a are not so narrow. ‘a’ is set to its natural width, and ‘b’ is set to `\tymmin`.

```
\tym{min}=20pt  
\tym{max}=200pt
```

In the previous example, the large d column dominated the table, being a lot wider than the c column. By reducing `\tymax` can limit the width of column d producing more even column widths, but now producing an entry for d that is longer than that for c.

## 5 The Code

```

1  {*package}
2 \RequirePackage{array}
3 \catcode`\Z=14
4 \DeclareOption{debugshow}{\catcode`\Z=9\relax}
5 \ProcessOptions

\arraybackslash Borrowed from tabularx.
6 \def\arraybackslash{\let\\=\@arraycr}

\@finalstrut Bug fixed version from December 1995 LATEX release. Old bug going back to
LATEX2.09...
7 \def\@finalstrut#1{%
8   \unskip\ifhmode\nobreak\fi\vrule\@width\z@\@height\z@\@depth\dp#1}

\TY@count Counter so that we know what column we are hacking around in.
9 \newcount\TY@count

\tabulary Top level macro for standard form.
10 \def\tabulary{%
11   \let\TY@final\tabular
12   \let\endTY@final\endtabular
13   \TY@tabular}

\TY@tabular Looks a lot like tabularx at this stage. Grab everything into a token register.
14 \def\TY@tabular#1{%
15   \edef\TY@{\@currenvir}%
16   {ifnum0='}\fi

At this point need to save locally things that tabulary will globally mess up. These
are restored at the end of the environment.
17   \@ovxx\TY@linewidth
18   \@ovyy\TY@tablewidth
19   \count@\z@
20   \tempswatrue
21   \whilesw\if@tempswa\fi{%
22     \advance\count@\@ne
23     \expandafter\ifx\csname TY@F\the\count@\endcsname\relax
24       \tempswafalse
25     \else
26       \expandafter\let\csname TY@SF\the\count@\expandafter\endcsname
27           \csname TY@F\the\count@\endcsname
28       \global\expandafter\let\csname TY@F\the\count@\endcsname\relax
29       \expandafter\let\csname TY@S\the\count@\expandafter\endcsname
30           \csname TY@\the\count@\endcsname
31     \fi}%
32   \global\TY@count\@ne
33   \TY@width\xdef{0pt}%
34   \global\TY@tablewidth\z@
35   \global\TY@linewidth#1\relax
36 Z\message{^^J^^JTable^^J%}

```

```

37 Z      Target Width: \the\TY@linewidth^~J%
38 Z      \string\tabcolsep: \the\tabcolsep\space
39 Z      \string\arrayrulewidth: \the\arrayrulewidth\space
40 Z      \string\doublerulesep: \the\doublerulesep^~J%
41 Z      \string\tymin: \the\tymin\space
42 Z      \string\tymax: \the\tymax^~J}%

```

Placing this here means that nested tabulars will get this definition but that's probably OK, the extra code for LCR etc shouldn't do any harm

```

43   \let\@classz\TY@classz
44   \let\verb\TX@verb
45   \toks@\{}TY@get@body\}

```

\TY@@mkpream Saved version.

```
46 \let\TY@@mkpream\@mkpream
```

\TY@mkpream TY version.

```

47 \def\TY@mkpream{%
48   \def\@addamp{%
49     \if@firstamp \else \global\advance\TY@count\@ne
50     \edef\@preamble{\@preamble &}\fi
51     \TY@width\xdef{0pt}}%
52   \def\@acol{%
53     \TY@subwidth\col@sep
54     \addtopreamble{\hspace{\col@sep}}%
55   }
56   \let\@arrayrule\TY@arrayrule
57   \let\@classvi\TY@classvi
58   \def\@classv{\@save@decl
59     \expandafter\NC@ecs\@nextchar\extracolsep{}\extracolsep\@@%
60     \sbox\z@\{\d@llarbegin\@nextchar\d@llarend\}%
61     \TY@subwidth{\wd\z@}%
62     \addtopreamble{\d@llarbegin\the\toks\the\count@\relax\d@llarend}%
63     \prepnext@tok}%
64   \global\let\@mkpream\TY@@mkpream
65   \TY@mkpream}

```

\TY@arrayrule Pull this out so the colortbl support below can redefine

```

66 \def\TY@arrayrule{%
67   \TY@subwidth\arrayrulewidth
68   \addtopreamble \vline}

```

\TY@classvi Pull this out so the colortbl support below can redefine

```

69 \def\TY@classvi{\ifcase \lastchclass
70   \@acol \or
71   \TY@subwidth\doublerulesep
72   \addtopreamble{\hspace{\doublerulesep}}\or
73   \@acol \or
74   \@classvii
75   \fi}

```

\TY@tab First run a tabular with all the column types fudged so that the widths of any rules or @-expressions are noted.

```

76 \def\TY@tab{%
77   \setbox\z@\hbox\bgroup

```

Support displaymath by making it non-display in the first pass. (Other display environments defined in terms of \$\$ would need to be added here by packages that define them.)

```

78   \let\[ \$\let\] $%
79   \let\equation$ \let\endequation$%
80   \col@sep\tabcolsep
81   \let\dollarbegin\begingroup\let\dollarend\endgroup
82   \let\mkpream\TY@mkpream
83   \def\multicolumn##1##2##3{\multispan##1\relax}%
84   \CT@start\TY@tabarray

```

\TY@tabarray

```

85 \def\TY@tabarray{\ifnextchar[{\TY@array}{\@array[t]}}
86 \def\TY@array[#1]{\@array[t]}

```

\TY@width Just a shorthand to access a column width macro.

```

87 \def\TY@width#1{%
88   \expandafter#1\csname TY@\the\TY@count\endcsname}

```

\TY@subwidth Subtract a width from the current column width and also The total line table width and the target line width.

```

89 \def\TY@subwidth#1{%
90   \TY@width\dimen@
91   \advance\dimen@-#1\relax
92   \TY@width\xdef{\the\dimen@}%
93   \global\advance\TY@linewidth-#1\relax}

```

\endtabulary First run one modified tabular, making sure to add a blank row (cf longtable) to the end in case the user supplied last row is hidden by an hline or something.

```

94 \def\endtabulary{%
95   \gdef\@haligno{}%
96   \expandafter\TY@tab\the\toks@
97   \crcr\omit
98   {\xdef\TY@save@row{}%
99     \loop
100    \advance\TY@count\m@ne
101    \ifnum\TY@count>\z@
102    \xdef\TY@save@row{\TY@save@row\&\omit}%
103    \repeat\TY@save@row
104  \endarray\global\setbox1=\lastbox\setbox0=\vbox{\unvbox1
105  \unskip\global\setbox1=\lastbox}\egroup

```

Check that \tymin is not too large.

```

106 \dimen@\TY@linewidth
107 \divide\dimen@\TY@count
108 \ifdim\dimen@<\tymin
109   \TY@warn{tymin too large (\the\tymin), resetting to \the\dimen@}%
110   \tymin\dimen@
111 \fi

```

Now take the last row apart, cf longtable or appendix D.

```

112  \setbox\tw@=\hbox{\unhbox\@ne
113   \loop
114   \tempdima=\lastskip
115   \ifdim\tempdima>\z@
116 Z    \message{ecs=\the\tempdima^~J}%
117   \global\advance\TY@linewidth-\tempdima
118 \fi
119   \unskip
120   \setbox\tw@=\lastbox
121   \ifhbox\tw@
122 Z    \message{Col \the\TY@count: Initial=\the\wd\tw@\space}%
123   \ifdim\wd\tw@>\tymax
124     \wd\tw@\tymax
125 Z    \message{> max\space}%
126 Z    \else
127 Z     \message{@spaces\space}%
128 \fi
129   \TY@width\dimen@
130 Z \message{\the\dimen@\space}%
131   \advance\dimen@\wd\tw@
132 Z \message{Final=\the\dimen@\space}%
133   \TY@width\xdef{\the\dimen@}%
134   \ifdim\dimen@<\tymin
135 Z    \message{< tymin}%
136   \global\advance\TY@linewidth-\dimen@
137   \expandafter\xdef\csname TY@F\the\TY@count\endcsname
138                                     {\the\dimen@}%
139   \else
140   \expandafter\ifx\csname TY@F\the\TY@count\endcsname\z@
141 Z    \message{***}%
142   \global\advance\TY@linewidth-\dimen@
143   \expandafter\xdef\csname TY@F\the\TY@count\endcsname
144                                     {\the\dimen@}%
145   \else
146 Z    \message{> tymin}%
147   \global\advance\TY@tablewidth\dimen@
148   \global\expandafter\let\csname TY@F\the\TY@count\endcsname
149                                     \maxdimen
150   \fi\fi
151   \advance\TY@count\m@ne
152 \repeat}%

```

A bit cheap just doing this four times, but prevents any possibilities of looping....

```

153   \TY@checkmin
154   \TY@checkmin
155   \TY@checkmin
156   \TY@checkmin

```

Reset the counter.

```
157   \TY@count\z@
```

Reset the LCRJ column definition to set paragraphs to the calculated widths.

```
158   \let\TY@box\TY@box@v
```

Run a second tabular, and for the star form, unbox it.

```
159  {\expandafter\TY@final\the\toks@\endTY@final}%
   Finish off by restoring global commands.
160  \count@\z@
161  \tempswattrue
162  \whilesw\if@tempswa\fi{%
163  \advance\count@\@ne
164  \expandafter\ifx\csname TY@SF\the\count@\endcsname\relax
165  \tempswafalse
166  \else
167  \global\expandafter\let\csname TY@F\the\count@\expandafter\endcsname
168  \csname TY@SF\the\count@\endcsname
169  \global\expandafter\let\csname TY@\the\count@\expandafter\endcsname
170  \csname TY@S\the\count@\endcsname
171  \fi}%
172  \TY@linewidth\@ovxx
173  \TY@tablewidth\@ovyy
174  \ifnum0='{\fi}}
```

\TY@checkmin Check that no column is squeezed below \tymin. If it is, fix the width of that column to \tymin and try again re-computing the ratio. (The new ratio will be smaller, and may squeeze yet more rows, so need to iterate this, currently just do it four times.)

```
175 \def\TY@checkmin{%
176  \let\TY@checkmin\relax
177 \ifdim\TY@tablewidth>\z@
178  \Gscale@div\TY@ratio\TY@linewidth\TY@tablewidth
179 % \changes{v0.9}{2008/12/01}
180 %     {\cs{TY@linewidth}}
181 \ifdim\TY@tablewidth <\TY@linewidth
182  \def\TY@ratio{1}%
183 \fi
184 \else
185  \TY@warn{No suitable columns!}%
186  \def\TY@ratio{1}%
187 \fi
188 \count@\z@
189 Z \message{^^JLine Width: \the\TY@linewidth,
190 Z           Natural Width: \the\TY@tablewidth,
191 Z           Ratio: \TY@ratio^^J}%
192 \tempdima\z@
193 \loop
194 \ifnum\count@<\TY@count
195 \advance\count@\@ne
196 \ifdim\csname TY@F\the\count@\endcsname>\tymin
197  \dimen@\csname TY@\the\count@\endcsname
198  \dimen@\TY@ratio\dimen@
199  \ifdim\dimen@<\tymin
200 Z   \message{Column \the\count@\space ->}%
201  \global\expandafter\let\csname TY@F\the\count@\endcsname\tymin
202  \global\advance\TY@linewidth-\tymin
203  \global\advance\TY@tablewidth-\csname TY@\the\count@\endcsname
```

```

204      \let\TY@checkmin\TY@@checkmin
205      \else
206          \expandafter\xdef\csname TY@F\the\count@\endcsname{\the\dimen@}%
207          \advance\@tempdima\csname TY@F\the\count@\endcsname
208      \fi
209  \fi
210 Z \dimen@\csname TY@F\the\count@\endcsname\message{\the\dimen@, }%
211 \repeat
212 Z \message{^JTotal:\the\@tempdima^J}%
213 }

\TY@@checkmin Saved value
214 \let\TY@@checkmin\TY@checkmin

TY@linewidth Stores the target width.
215 \newdimen\TY@linewidth

\tyformat What to do with columns
216 \def\tyformat{\everypar{{\nobreak\hskip\z@skip}}}

tymin Columns narrower than this are not fudged.
217 \newdimen\tymin
218 \tymin=10pt

tymin Columns wider than this are all treated alike and set to the same width, to stop
one particularly long entry hijacking the entire table.
219 \newdimen\tymax
220 \tymax=2\textwidth

@testpatch Also add LCRJ although these don't do anything useful except in tabulary.
221 \def@testpach{\chclass
222 \ifnum \lastchclass=6 \one \chnum \one \else
223 \ifnum \lastchclass=7 5 \else
224 \ifnum \lastchclass=8 \tw@ \else
225 \ifnum \lastchclass=9 \thr@%
226 \else \z@
227 \ifnum \lastchclass = 10 \else
228 \edef\@nextchar{\expandafter\string\@nextchar}%
229 \chnum
230 \if \@nextchar c\z@ \else
231 \if \@nextchar l\one \else
232 \if \@nextchar r\tw@ \else
233 \if \@nextchar s6 \else
234 \if \@nextchar C7 \else
235 \if \@nextchar L8 \else
236 \if \@nextchar R9 \else
237 \if \@nextchar J10 \else
238 \z@ \chclass
239 \if\@nextchar |\one \else
240 \if \@nextchar !6 \else
241 \if \@nextchar @7 \else
242 \if \@nextchar <8 \else

```

```

243      \if \@nextchar >9 \else
244      10
245      \chnum
246      \if \@nextchar m\thr@ \else
247      \if \@nextchar p4 \else
248      \if \@nextchar b5 \else
249      \z@ \chclass \z@ \preamerr \z@ \fi \fi \fi \fi \fi \fi \fi \fi
250 %
251      \fi
251      \fi \fi

```

\TY@classz Here hacked around without the respect Frank's code deserves...

```

252 \def\TY@classz{%
253   \classx
254   \tempcnta\count@
255   \ifx\TY@box\TY@box@v
256     \global\advance\TY@count\@ne
257   \fi
258   \let\centering c%
259   \let\raggedright\noindent
260   \let\raggedleft\indent
261   \let\arraybackslash\relax
262   \prepnext@tok
263   \ifnum\chnum<4
264     \global\expandafter\let\csname TYF\the\TY@count\endcsname\z@
265   \fi
266   \ifnum\chnum=6
267     \global\expandafter\let\csname TYF\the\TY@count\endcsname\z@
268   \fi
269   \addtopreamble{%
270     \ifcase\chnum
271       \hfil \d@llarbegin\insert@column\d@llarend \hfil \or
272       \kern\z@
273       \d@llarbegin \insert@column \d@llarend \hfil \or
274       \hfil\kern\z@ \d@llarbegin \insert@column \d@llarend \or
275       \$\vcenter\@startpbox{\@nextchar}\insert@column \endpbox \$\or
276       \vtop\@startpbox{\@nextchar}\insert@column \endpbox \or
277       \vbox\@startpbox{\@nextchar}\insert@column \endpbox \or
278       \d@llarbegin \insert@column \d@llarend \or% dubious "s" case
279       \TY@box\centering\or
280       \TY@box\raggedright\or
281       \TY@box\raggedleft\or
282       \TY@box\relax
283   \fi}\prepnext@tok}

```

\TY@box The argument is \centering etc depending on whether LCRJ is used. However in this version the entries are set in horizontal mode with definitions mimicing the standard lcr columns. Later \TY@box will be redefined to \TY@box@v which really sets the entries in vertical mode.

```

284 \def\TY@box#1{%
285   \ifx\centering#1%
286     \hfil \d@llarbegin\insert@column\d@llarend \hfil \else
287   \ifx\raggedright#1%
288     \kern\z@%%%%%%%%%%%%%
289     \d@llarbegin \insert@column \d@llarend \hfil \else

```

```

290   \ifx\raggedleft#1%
291     \hfil\kern\z@\dollarbegin \insert@column \dollarend \else
292   \ifx\relax#1%
293     \dollarbegin \insert@column \dollarend
294   \fi \fi \fi \fi}

\TY@box@v The version to use in a final run, set the CLRJ columns in a parbox of the appropriate width.
295 \def\TY@box@v#1{%
296   \vtop \startpbox{\csname TY@F\the\TY@count\endcsname}%
297   #1\arraybackslash\tyformat
298   \insert@column\endpbox}

\TY@tablewidth The natural width of the table on the first run.
299 \newdimen\TY@tablewidth

\Gscale@div Stolen from graphics package.
300 \def\Gscale@div#1#2#3{%
301   \setlength\dimen@{#3}%
302   \ifdim\dimen@=\z@
303     \PackageError{graphics}{Division by 0}\@eha
304     \dimen@#2%
305   \fi
306   \edef\@tempd{\the\dimen@}%
307   \setlength\dimen@{#2}%
308   \count@65536\relax
309   \ifdim\dimen@<\z@
310     \dimen@-\dimen@
311     \count@-\count@
312   \fi
313   \loop
314   \ifdim\dimen@<8192\p@
315     \dimen@\tw@\dimen@
316     \divide\count@\tw@
317   \repeat
318   \dimen@ii=\@tempd\relax
319   \divide\dimen@ii\count@
320   \divide\dimen@\dimen@ii
321   \edef#1{\strip@pt\dimen@}}}

\TY@get@body Place all tokens as far as the first \end into a token register. Then call \TY@find@end to see if we are at \end{tabulary}.
322 \long\def\TY@get@body#1\end
323 { \toks@\expandafter{\the\toks@#1}\TY@find@end}

\TY@find@end If we are at \end{tabulary}, call \end{tabulary}, otherwise add \end{...} to the register, and call \TY@get@body again.
324 \def\TY@find@end#1{%
325   \def\@tempa{#1}%
326   \ifx\@tempa\TY@def\@tempa{\end{#1}}\expandafter\@tempa
327   \else\toks@\expandafter
328   {\the\toks@\end{#1}}\expandafter\TY@get@body\fi}

```

```

\TY@warn Warning messages.

329 \def\TY@warn{%
330   \PackageWarning{tabulary}{%
331     \catcode`\Z=11
332     colortbl support.%
333   }%
334   \AtBeginDocument{%
335     \IfPackageLoaded{colortbl}{%
336       \expandafter\def\expandafter\@mkpream\expandafter#\expandafter1\%
337         \expandafter\let\expandafter\CT@setup\expandafter\relax
338         \expandafter\let\expandafter\CT@color\expandafter\relax
339         \expandafter\let\expandafter\CT@do@color\expandafter\relax
340         \expandafter\let\expandafter\color\expandafter\relax
341         \expandafter\let\expandafter\CT@column@color\expandafter\relax
342         \expandafter\let\expandafter\CT@row@color\expandafter\relax
343         \expandafter\@mkpream{\#1}%
344       \let\TY@@mkpream\@mkpream
345       \def\TY@classz{%
346         \classx
347         \tempcnta\count@
348         \ifx\TY@box\TY@box@v
349           \global\advance\TY@count\@ne
350         \fi
351         \centering c%
352         \raggedright\noindent
353         \raggedleft\indent
354         \arraybackslash\relax
355         \prepnext@tok
356       \expandafter\CT@extract\the\toks\tempcnta\columncolor!\@nil
357       \ifnum\@chnum<4
358         \global\expandafter\let\csname TY@F\the\TY@count\endcsname\z@
359       \fi
360       \ifnum\@chnum=6
361         \global\expandafter\let\csname TY@F\the\TY@count\endcsname\z@%
362       \fi
363       \addtopreamble{%
364         \setbox\z@\hbox\bgroup\bgroup
365         \ifcase\@chnum
366           \hskip\stretch{.5}\kern\z@
367           \d@llarbegin\insert@column\d@llarend\hskip\stretch{.5}\or
368           \kern\z@<<<<<<<<<<<<<<<
369           \d@llarbegin\insert@column\d@llarend\hfill\or
370           \hfill\kern\z@\d@llarbegin\insert@column\d@llarend\or
371           \$\vcenter\@startpbox{\@nextchar}\insert@column\@endpbox\$%
372           \vtop\@startpbox{\@nextchar}\insert@column\@endpbox\or
373           \vbox\@startpbox{\@nextchar}\insert@column\@endpbox\or
374           \d@llarbegin\insert@column\d@llarend\or% dubious s case
375           \TY@box\centering\or
376           \TY@box\raggedright\or
377           \TY@box\raggedleft\or
378           \TY@box\relax
379         \fi
380       }%
381     }%
382   }%
383 }%

```

```

379 \egroup\egroup
380 \begingroup
381 \CT@setup
382 \CT@column@color
383 \CT@row@color
384 \CT@do@color
385 \endgroup
386     \tempdima\ht\z@
387     \advance\tempdima\minrowclearance
388     \vrule\height\tempdima\width\z@
389 \unhbox\z@
390 }\prepnext@tok}%
391 \def\TY@arrayrule{%
392     \TY@subwidth\arrayrulewidth
393     \caddtopreamble{\CT@arc@vline}}%
394 \def\TY@classvi{\ifcase \lastchclass
395     \acol \or
396     \TY@subwidth\doublerulesep
397     \ifx\CT@drsc@\relax
398         \caddtopreamble{\hskip\doublerulesep}}%
399     \else
400         \caddtopreamble{\CT@drsc@\vrule\width\doublerulesep}}%
401     \fi\or
402     \acol \or
403     \classvii
404     \fi}%
405 }{%
406 \let\CT@start\relax
407 }

```

end of at begin document

```

408 }

```

\TX@warn \verb support, uses same csnames as in TX so they share code if both loaded (this version names tabulary in the warning though). See tabularx for documentation.

```

409 {\uccode`*=`\ %
410 \uppercase{\gdef\TX@verb{%
411     \leavevmode\null\TX@vwarn
412     {\ifnum0='}\fi\ttfamily\let\\ignorespaces
413     \ifstar{\let~*\TX@vb}{\TX@vb}}}}
414 \def\TX@vb#1{\def\tempa##1{\toks@{##1}\edef\tempa{\the\toks@}%
415     \expandafter\TX@v\meaning\tempa\\ \ifnum0='{\fi}\tempa!}
416 \def\TX@v#1{\afterassignment\TX@vf\first\let\tempa= }
417 \begingroup
418 \catcode`*=`catcode`#
419 \catcode`\#=12
420 \gdef\TX@vf{\%
421     \if\tempa%
422         \def\tempb{\TX@v#}%
423     \else
424         \let\tempb\TX@v
425         \if\tempa\space~\else\tempa\fi
426     \fi

```

```
427   \tempb}
428 \gdef\TX@v@*1 *2{%
429   \TX@v@hash*1##\relax\if*2\\else`\expandafter\TX@v@\fi*2}
430 \gdef\TX@v@hash*1##*2{*1\ifx*2\relax\else#\expandafter\TX@v@hash\fi*2}
431 \endgroup
432 \def\TX@vwarn{%
433   \warning{\noexpand\verb may be unreliable inside tabularx/y}%
434   \global\let\TX@vwarn\empty}
435 </package>
```