

The `tocvsec2` package*

Author: Peter Wilson, Herries Press

Maintainer: Will Robertson

`will dot robertson at latex-project dot org`

2010/02/27

Abstract

The `tocvsec2` package provides means of controlling the sectional numbering and/or the entries in the Table of Contents on a section by section basis. It is a replacement for the `tocvsec` package, which should not be used. Use of the package requires the `ifthen` package to be available.

Contents

1	Introduction	1
2	The <code>tocvsec2</code> package	2
3	The package code	4

1 Introduction

In the standard classes two commands are used to control the numbering of sectional divisions in a document, and which level of sectional headings will be included in the Table of Contents (the ToC). Sometimes finer control of these aspects of \LaTeX is required. The `tocvsec2` provides for control over the entries into the ToC on a section by section basis. It also provides a means of locally controlling sectional numbering without having to resort to the starred version of the sectional commands. The package requires the `ifthen` package to be available.

Portions of the package were developed as part of a class and package bundle for typesetting ISO standards [Wil96]. This manual is typeset according to the conventions of the \LaTeX `DOCSTRIP` utility which enables the automatic extraction of the \LaTeX macro source files [GMS94].

*This file (`tocvsec2.dtx`) has version number v1.2b, last revised 2010/02/27.

Section 2 describes the usage of the package. Commented source code for the package is in Section 3.

`secnumdepth`

The L^AT_EX *secnumdepth* counter specifies the level number for the least significant sectional heading that will be numbered. In all the standard classes `\section` has a level number of 1, `\subsection` has a level number of 2, and so on. In the `article` class (and its derivatives), `\part` has a level number of 0. In the `book` and `report` classes, `\chapter` is level number 0 and `\part` has level number -1.

The *secnumdepth* counter is normally set in the preamble and remains constant thereafter. For example:

```
\setcounter{secnumdepth}{2}
```

specifies that `\subsections` and above should be numbered and `\subsubsections` and below should not be numbered. It turns out that *secnumdepth* can be changed at any point in a document, not just in the preamble, to make a (temporary) change to the section numbering level. This is possible because the heading commands check the value of *secnumdepth* to decide whether or not to number the heading.

`tocdepth`

The *tocdepth* counter specifies the level number of the least significant sectional unit that will be listed in the printed Table of Contents (ToC). For example:

```
\setcounter{tocdepth}{1}
```

specifies that the printed ToC should only list sectional headings down to the `\section` level. The value of *tocdepth* has to be set before the `\tableofcontents` command is used. Each sectioning command puts an entry into the `.toc` file, irrespective of the *tocdepth* value. The code implementing the typesetting of the ToC uses *tocdepth* to determine whether or not an entry should be printed. Thus, unlike *secnumdepth* which can be altered at any time and have an effect, it is only the value of *tocdepth* at the time of printing the entries in the `\tableofcontents` that is used — any subsequent changes to *tocdepth* are immaterial.

Note that *tocdepth* only controls what appears in the ToC, and *secnumdepth* only controls which sectional headings are numbered. The effect of changing one has no bearing on the other.

2 The `tocvsec2` package

The `tocvsec` package changed the way in which entries were written to the `.toc` file, enabling effective changes to be made to *tocdepth* at any point in a document.

The basis of that package was to ensure that only those sectional elements that were required to appear in the printed ToC were written to the `.toc` file. The sectional commands call the `\addcontentsline` command to write an entry to the `.toc` file. There were two methods to achieve the desired functionality, both of which required modifications to the internal L^AT_EX macros.

1. Modify the sectional commands so that they check the value of *tocdepth* in order to decide whether or not to put an entry into the *.toc* file (i.e., call `\addcontentsline`).
2. Modify `\addcontentsline` so that it decides whether or not to write to the *.toc* file. This is less efficient in terms of processing time than changing the sectional commands.

Both approaches had disadvantages. If the `tocvsec` package changed the sectional commands and it was used in conjunction with another package that also changes these definitions, then one or the other package would not work as expected. On the other hand, changing the `\addcontentsline` command may have had unexpected results if `\addcontentsline` was either modified or used in a different manner elsewhere in the document.

The `tocvsec2` package takes a different approach which does not have these disadvantages. It provides a means of inserting commands into the *.toc* file that change the current value of *tocdepth* within the body of the file.

The package also provides some utility commands so you don't have to remember the level numbers of the sectioning commands.

`\maxtocdepth` The `\maxtocdepth{<sec>}` command can be used after the preamble (and before the `\tableofcontents` command) to set the global value for the *tocdepth*. *<sec>* is the name of a sectioning division (e.g., `part` or `paragraph`). You can also use `all`, meaning all sectioning divisions, or `none`, meaning no sectioning divisions.

`\settocdepth` The `\settocdepth{<sec>}` command can be used to change the value of the *tocdepth* counter within the *.toc* file, where *<sec>* is the name of a sectional division (e.g., `chapter` or `subsection`), or `all` or `none`. For example, `\settocdepth{section}` will set *tocdepth* to be 1 within the *.toc* file, until it is altered by another `\settocdepth` command. The command cannot be used in the preamble (i.e., before `\begin{document}`), but can be used any point thereafter.

tocdepth should be set in the preamble, or immediately after, to the least significant sectional unit that should be in the printed ToC. Later, after the `\tableofcontents` command, it is possible to use `\settocdepth` to reset *tocdepth* to a more significant sectional level (and to reset it back again). As an example, assume that the ToC should list subsections and above, but there is one particular section in the document which consists of a set of definitions, each of which is presented as a subsection, but these should not appear in the printed ToC.

```

\documentclass{...}
\usepackage{tocvsec2}
...
\begin{document}
    \maxtocdepth{subsection}
    ...
\tableofcontents
    ...
\section{Definitions}
    \settocdepth{section}

```

```

\subsection{Definition 1}
...
\settocdepth{subsection}
\section{After definitions}
...

```

`\setsecnumdepth` The `\setsecnumdepth{<sec>}` command is similar to `\settocdepth` except that it changes the value of `secnumdepth` at the point in the document where it is called. Like the `\settocdepth` command, it cannot be used in the preamble, but can be used as often as necessary after that.

`\maxsecnumdepth` The `\maxsecnumdepth{<sec>}` command is similar to `\maxtocdepth` except that it is for setting the default value for `secnumdepth` after the preamble. If you used `\setsecnumdepth` for this purpose you might find an extra blank page in the typeset manuscript.

For example, assume that in a document the sectional divisions are normally numbered down to the sub-subsection level, but within a particular section, they should only be numbered to the subsection level. Also, all sectional divisions within the appendices are to be numbered. This can be accomplished like:

```

\documentclass{...}
\usepackage{tocvsec2}
...
\begin{document}
\maxsecnumdepth{subsubsection}
...
\tableofcontents
...
\section{Normal section}
...
\section{Reduce numbering}
\setsecnumdepth{subsection}
...
\setsecnumdepth{subsubsection}
\section{Another normal section}
...
\appendix
\setsecnumdepth{all}
...

```

3 The package code

```

1 <*usc>
2 \RequirePackage{ifthen}

```

In order to try and avoid name clashes with other packages, each internal name will include the character string `t@c`.

Issue warning if there are no recognized sectional divisions.

```

3 \newif\ift@cchapter
4 \t@cchapterfalse
5 \@ifundefined{chapter}{%
6 \@ifundefined{section}{%
7 \PackageWarning{tocvsec2}{%
8 I don't recognize any divisions but I'll do my best}}{}}%
9 {\t@cchaptertrue}
10
\if@knownsect@c A helper macro to set a sectioning-related counter. Call as \setsecntt@c{<sec>}{<counter>}
\@setsecntt@c to set <counter> to the level of <sec>.
11 \newif\if@knownsect@c
12 \newcommand{\@setsecntt@c}[2]{
13 \@knownsect@cfalse
14 \ifthenelse{\equal{#1}{none}}{\setcounter{#2}{-10}
15 \@knownsect@ctrue}{%
16 \ifthenelse{\equal{#1}{part}}{\ift@cchapter
17 \setcounter{#2}{-1}
18 \else
19 \setcounter{#2}{0}
20 \fi
21 \@knownsect@ctrue}{%
22 \ifthenelse{\equal{#1}{chapter}}{\setcounter{#2}{0}
23 \@knownsect@ctrue}{%
24 \ifthenelse{\equal{#1}{section}}{\setcounter{#2}{1}
25 \@knownsect@ctrue}{%
26 \ifthenelse{\equal{#1}{subsection}}{\setcounter{#2}{2}
27 \@knownsect@ctrue}{%
28 \ifthenelse{\equal{#1}{subsubsection}}{\setcounter{#2}{3}
29 \@knownsect@ctrue}{%
30 \ifthenelse{\equal{#1}{paragraph}}{\setcounter{#2}{4}
31 \@knownsect@ctrue}{%
32 \ifthenelse{\equal{#1}{subparagraph}}{\setcounter{#2}{5}
33 \@knownsect@ctrue}{%
34 \ifthenelse{\equal{#1}{all}}{\setcounter{#2}{100}
35 \@knownsect@ctrue}{%
36 \if@knownsect@c\else
37 \PackageError{tocvsec2}{%
38 Unknown sectioning command name (#1)
39 }{%
40 I'll ignore it. Type \space <return> and I'll continue.\MessageBreak
41 If you haven't mistyped the name then use \protect\setcounter\space instead.}
42 \fi
43 }

\settocdepth \settocdepth{<sec>} is the user command for setting <tocdepth> in the .toc file to
the value corresponding to <sec>.
44 \newcommand{\settocdepth}[1]{%
45 \@knownsect@cfalse
46 \ifthenelse{\equal{#1}{none}}{%

```

```

47   \addtocontents{toc}{\protect\setcounter{tocdepth}{-10}}
48   \@knownsect@ctrue{}}
49 \ifthenelse{\equal{#1}{part}}{%
50   \ift@cchapter
51     \addtocontents{toc}{\protect\setcounter{tocdepth}{-1}}
52   \else
53     \addtocontents{toc}{\protect\setcounter{tocdepth}{0}}
54   \fi
55   \@knownsect@ctrue{}}
56 \ifthenelse{\equal{#1}{chapter}}{%
57   \addtocontents{toc}{\protect\setcounter{tocdepth}{0}}
58   \@knownsect@ctrue{}}
59 \ifthenelse{\equal{#1}{section}}{%
60   \addtocontents{toc}{\protect\setcounter{tocdepth}{1}}
61   \@knownsect@ctrue{}}
62 \ifthenelse{\equal{#1}{subsection}}{
63   \addtocontents{toc}{\protect\setcounter{tocdepth}{2}}
64   \@knownsect@ctrue{}}
65 \ifthenelse{\equal{#1}{subsubsection}}{%
66   \addtocontents{toc}{\protect\setcounter{tocdepth}{3}}
67   \@knownsect@ctrue{}}
68 \ifthenelse{\equal{#1}{paragraph}}{%
69   \addtocontents{toc}{\protect\setcounter{tocdepth}{4}}
70   \@knownsect@ctrue{}}
71 \ifthenelse{\equal{#1}{subparagraph}}{%
72   \addtocontents{toc}{\protect\setcounter{tocdepth}{5}}
73   \@knownsect@ctrue{}}
74 \ifthenelse{\equal{#1}{all}}{%
75   \addtocontents{toc}{\protect\setcounter{tocdepth}{100}}
76   \@knownsect@ctrue{}}
77 \if@knownsect@c\else
78   \PackageError{tocvsec2}{%
79     Unknown sectioning command name (#1)}%
80     {I'll ignore it. Type \space <return> and I'll continue.}
81 \fi
82 }

```

`\maxtocdepth` `\maxtocdepth{<sec>}` can be used to initialise `tocdepth` between the end of the preamble and the `\tableofcontents` command.

```

83 \newcommand{\maxtocdepth}[1]{
84   \@setseccntt@c{#1}{tocdepth}}

```

`\setsecnumdepth` `\setsecnumdepth{<sec>}` is the user command for setting `secnumdepth` to the value corresponding to `<sec>`.

```

85 \newcommand{\setsecnumdepth}[1]{%
86   \@setseccntt@c{#1}{secnumdepth}}

```

`\maxsecnumdepth` `\maxsecnumdepth{<sec>}` is the user command to initialise `secnumdepth` after the preamble to the value corresponding to `<sec>`.

```

87 \newcommand{\maxsecnumdepth}[1]{%
88 \setsecntt@c{#1}{secnumdepth}}

```

The end of this package.

```
89 </usc>
```

References

- [GMS94] Michel Goossens, Frank Mittelbach, and Alexander Samarin. *The LaTeX Companion*. Addison-Wesley Publishing Company, 1994.
- [Wil96] Peter R. Wilson. *LaTeX for standards: The LaTeX package files user manual*. NIST Report NISTIR, June 1996.

Index

Numbers written in *italic* refer to the page where the corresponding entry is described; numbers underlined refer to the code line of the definition; numbers in *roman* refer to the code lines where the entry is used.

Symbols	16, 22, 24, 26,	N
<code>\@ifundefined</code>	5, 6	<code>\newif</code>
<code>\@knownsect@cfalse</code> .	46, 49, 56, 59,	
.	13, 45	P
<code>\@knownsect@ctrue</code>	15,	<code>\PackageError</code> . . .
21, 23, 25, 27,		<code>\PackageWarning</code>
29, 31, 33, 35,		
48, 55, 58, 61,		R
64, 67, 70, 73, 76		<code>\RequirePackage</code>
<code>\@setsecntt@c</code>		
. . . . <u>11</u> , 84, 86, 88		S
A		<code>\secnumdepth</code>
<code>\addtocontents</code> .	47,	<code>\setsecnumdepth</code> . . .
51, 53, 57, 60,		<code>\settocdepth</code>
63, 66, 69, 72, 75		
E		
<code>\equal</code>	14,	
		T
		<code>\tccchapterfalse</code> . . .
		<code>\tccchaptertrue</code>
		<code>\tocdepth</code>
	I	
	<code>\if@knownsect@c</code> .	<u>11</u> , 77
	<code>\iftccchapter</code> .	3, 16, 50
	<code>\ifthenelse</code>	14,
	16, 22, 24, 26,	
	28, 30, 32, 34,	
	46, 49, 56, 59,	
	62, 65, 68, 71, 74	
	M	
	<code>\maxsecnumdepth</code> . .	4, <u>87</u>
	<code>\maxtocdepth</code>	3, <u>83</u>
	<code>\MessageBreak</code>	40